

# The particle diagnostic in SMILEI

F. Pérez

March 19, 2015

The *particle diagnostic* collects data from the macro-particles and processes them during runtime. It does not provide information on individual particles: instead, it produces averaged quantities like the particle density, currents, etc.

The data may be collected from one or several particle species.

The data is discretized inside a “grid” chosen by the user. This grid may be of any dimension. Examples:

- 1-dimensional grid along the position  $x$  (gives density variation along  $x$ )
- 2-dimensional grid along positions  $x$  and  $y$  (gives density map)
- 1-dimensional grid along the velocity  $v_x$  (gives the velocity distribution)
- 2-dimensional grid along position  $x$  and momentum  $p_x$  (gives the phase-space)
- 1-dimensional grid along the kinetic energy  $E_{\text{kin}}$  (gives the energy distribution)
- 3-dimensional grid along  $x$ ,  $y$  and  $E_{\text{kin}}$  (gives the density map for several energies)
- 1-dimensional grid along the charge  $Z^*$  (gives the charge distribution)

Each dimension of the grid is called “axis”.

The user may choose to average the data over several time-steps.

# 1 How to add a particle diagnostic in the input file

In the input file, you can add a particle diagnostic with the following syntax.

```
diagnostic particles
  output = output
  every = every
  time_average = time_average
  species = species1 species2 ...
  axis = type min max nsteps [logscale] [edge_inclusive]
  axis = type min max nsteps [logscale] [edge_inclusive]
  ...
end
```

- *output* must be set to `density`, `current_density_x`, `current_density_y`, `current_density_z`. It determines the data that is summed in each cell of the grid. In the case of `density`, the *weights* are summed. In the case of `current_density_x`, the *weights*×*v<sub>x</sub>* are summed (etc.)
- *every* must be a positive integer. It is the number of time-steps between each output.
- *time\_average* must be a positive integer. It is the number of time-steps during which the data is averaged before output.
- *species1 species2 ...* must be one or several species. Species are recognized by their parameter `species_type` that is included in each group `species ... end`
- *axis* is an argument that describes one axis of the grid.  
Syntax: `axis = type min max nsteps` [logscale] [edge\_inclusive]  
*type* can be `x`, `y`, `z`, `px`, `py`, `pz`, `gamma`, `ekin`, `vx`, `vy`, `vz` or `charge`.  
The axis is discretized for *type* from *min* to *max* in *nsteps* bins.  
The optional keyword `logscale` sets the axis scale to logarithmic instead of linear.  
The optional keyword `edge_inclusive` includes the particles outside the range [*min*, *max*] into the extrema bins.

There may be as many `axis` arguments as wanted in one `diagnostic particles` block.

There may be as many `diagnostic particles` blocks as wanted in the input file.

In the input file, you may add the following block as a reminder.

```
# DIAGNOSTICS ON PARTICLES - project the particles on a N-D arbitrary grid
# -----
# output = density or current_density_[xyz]
#           => parameter that describes what quantity is obtained
# every      => integer > 0 : number of time-steps between each output
# time_average => integer > 0 : number of time-steps to average
# species     => list of one or several species whose data will be used
# axis  = _type_ _min_ _max_ _nsteps_ [logscale] [edge_inclusive]
#           => _type_ can be one of the following:
#               x, y, z, px, py, pz, gamma, ekin, vx, vy, vz or charge
#           => the data is discretized for _type_ between _min_ and
#               _max_, in _nsteps_ bins
#           => the optional [logscale] sets the scale to logarithmic
#           => the optional [edge_inclusive] forces the particles
#               outside (_min_,_max_) to be counted in the extrema bins
# example : axis = x 0 1 30
# example : axis = px -1 1 100
# >>>> MANY AXES CAN BE ADDED IN A SINGLE DIAGNOSTIC <<<<
```

## 2 Examples

Variation of the density of species `electron1` from  $x = 0$  to 1, every 5 time-steps, without time-averaging.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
end
```

Density map from  $x = 0$  to 1,  $y = 0$  to 1.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
  axis = y      0      1      30
end
```

Velocity distribution from  $v_x = -0.1$  to 0.1.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = vx     -0.1    0.1    100
end
```

Phase space from  $x = 0$  to 1 and from  $px = -1$  to 1.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
  axis = px     -1      1     100
end
```

Energy distribution from 0.01 to 1 MeV in logarithmic scale. Note that the input units are  $m_e c^2 \sim 0.5$  MeV.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = ekin    0.02    2    100  logscale
end
```

$x$ - $y$  density maps for three bands of energy:  $[0, 1]$ ,  $[1, 2]$ ,  $[2, \infty]$ . Note the use of `edge_inclusive` to reach energies up to  $\infty$ .

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
  axis = y      0      1      30
  axis = ekin    0      6      3  edge_inclusive
end
```

Charge distribution from  $Z^* = 0$  to 10.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = charge  -0.5    10.5    11
end
```

### 3 How to view and post-process a particle diagnostic

Each diagnostic produces one file like *ParticleDiagnostic0.h5*, *ParticleDiagnostic1.h5*, etc. They are numbered the same way as the order of appearance in the input file.

A python script *ParticleDiagnostic.py* is provided to view or extract data from these files. To run this script, you will need *python2.7* with the following packages: numpy, matplotlib, pylab, h5py.

First, run python and include the script:

```
python -i ParticleDiagnostic.py
```

(Alternately, you can include this file into your own script using, for example,

```
execfile("scripts/ParticleDiagnostic.py") )
```

From the python prompt, you can run the function *ParticleDiagnostic* which can extract the diagnostic data and optionally display it in a graph window.

Syntax of the function *ParticleDiagnostic*:

```
ParticleDiagnostic(results_path, diagNumber=None, timesteps=None, slice=None,
                  units="code", data_log=False, data_min=None, data_max=None,
                  xmin=None, xmax=None, ymin=None, ymax=None,
                  figure=None)
```

- `results_path = _string_`

Path to the directory where the outputs are stored.

(Also, this has to contain one and only one input file \*.in)

- `diagNumber = _int_` (optional)

Number of the diagnostic. The first diagnostic has number 0.

If not given, then a list of available diagnostics is printed.

- `timesteps = _int_` (optional)

`timesteps = [_int_, _int_] (optional)`

If omitted, all timesteps are used.

If one number given, the nearest timestep available is used.

If two numbers given, all the timesteps in between are used.

- `slice = { axis : "all", ... } (optional)`

`slice = { axis : _double_, ... } (optional)`

`slice = { axis : [_double_, _double_], ... } (optional)`

This parameter is used to reduce the number of dimensions of the array.

`axis` must be "x", "y", "z", "px", "py", "pz", "p", "gamma", "ekin", "vx", "vy", "vz", "v" or "charge".

Any axis of the same name will be removed with the following technique:

- If the value is "all", then a sum is performed over all the axis.

- If the value is \_double\_, then only the bin closest to the value is kept.

- If the value is [\_double\_, \_double\_] , then a sum is performed between the two values.

Example: `{"x": [4,5]}` will sum all the data for x in the range [4,5].

- `units = "nice"` (optional)  
If "nice" is chosen, then units are converted into usual units.  
Distances in microns, density in  $\text{cm}^{-3}$ , energy in MeV.
- `data_log = True` or (`False`) (optional)  
If True, then log 10 is applied to the output array before plotting.
- `data_min = _double_` (optional)  
`data_max = _double_` (optional)  
If present, output is rescaled before plotting.
- `xmin = _double_` (optional)  
`xmax = _double_` (optional)  
`ymin = _double_` (optional)  
`ymax = _double_` (optional)  
If present, axes are rescaled before plotting.
- `figure = None` (default)  
`figure = _int_` (optional)  
Chooses the figure number that is passed to matplotlib.  
If absent or None, returns the first data without plotting.

Example of usage from the python prompt:

```
>>> ParticleDiagnostic("path/to/my/results", diagNumber=1, slice={"y":"all"},
    units="nice", data_min=0, data_max=3e14, figure=1)
```

This will take the diagnostic #1, and sum the grid over all the  $y$  axis. Then it will plot the resulting array in figure 1 from 0 to 3e14.