

The particle diagnostic in SMILEI

F. Pérez

March 19, 2015

The *particle diagnostic* collects data from the macro-particles and processes them during runtime. It does not provide information on individual particles: instead, it produces averaged quantities like the particle density, currents, etc.

The data may be collected from one or several particle species.

The data is discretized inside a “grid” chosen by the user. This grid may be of any dimension. Examples:

- 1-dimensional grid along the position x (gives density variation along x)
- 2-dimensional grid along positions x and y (gives density map)
- 1-dimensional grid along the velocity v_x (gives the velocity distribution)
- 2-dimensional grid along position x and momentum p_x (gives the phase-space)
- 1-dimensional grid along the kinetic energy E_{kin} (gives the energy distribution)
- 3-dimensional grid along x , y and E_{kin} (gives the density map for several energies)
- 1-dimensional grid along the charge Z^* (gives the charge distribution)

Each dimension of the grid is called “axis”.

The user may choose to average the data over several time-steps.

1 How to add a particle diagnostic in the input file

In the input file, you can add a particle diagnostic with the following syntax.

```
diagnostic particles
  output = output
  every = every
  time_average = time_average
  species = species1 species2 ...
  axis = type min max nsteps [logscale] [edge_inclusive]
  axis = type min max nsteps [logscale] [edge_inclusive]
  ...
end
```

- *output* must be set to `density`, `charge_density`, `current_density_x`, `current_density_y`, `current_density_z`. It determines the data that is summed in each cell of the grid. In the case of `density`, the *weights* are summed. In the case of `charge_density`, the *weights*×*charge* are summed. In the case of `current_density_x`, the *weights*×*charge*×*v_x* are summed (etc.)
- *every* must be a positive integer. It is the number of time-steps between each output.
- *time_average* must be a positive integer. It is the number of time-steps during which the data is averaged before output.
- *species1 species2 ...* must be one or several species. Species are recognized by their parameter `species_type` that is included in each group `species ... end`
- *axis* is an argument that describes one axis of the grid.
Syntax: `axis = type min max nsteps` [logscale] [edge_inclusive]
type can be `x`, `y`, `z`, `px`, `py`, `pz`, `p`, `gamma`, `ekin`, `vx`, `vy`, `vz`, `v` or `charge`.
The axis is discretized for *type* from *min* to *max* in *nsteps* bins.
The optional keyword `logscale` sets the axis scale to logarithmic instead of linear.
The optional keyword `edge_inclusive` includes the particles outside the range [*min*, *max*] into the extrema bins.

There may be as many `axis` arguments as wanted in one `diagnostic particles` block.

There may be as many `diagnostic particles` blocks as wanted in the input file.

In the input file, you may add the following block as a reminder.

```
# DIAGNOSTICS ON PARTICLES - project the particles on a N-D arbitrary grid
# -----
# output = density, charge_density or current_density_[xyz]
#           => parameter that describes what quantity is obtained
# every      => integer > 0 : number of time-steps between each output
# time_average => integer > 0 : number of time-steps to average
# species     => list of one or several species whose data will be used
# axis  = _type_ _min_ _max_ _nsteps_ [logscale] [edge_inclusive]
#           => _type_ can be one of the following:
#               x, y, z, px, py, pz, p, gamma, ekin, vx, vy, vz, v or charge
#           => the data is discretized for _type_ between _min_ and
#               _max_, in _nsteps_ bins
#           => the optional [logscale] sets the scale to logarithmic
#           => the optional [edge_inclusive] forces the particles
#               outside (_min_,_max_) to be counted in the extrema bins
# example : axis = x 0 1 30
# example : axis = px -1 1 100
# >>>> MANY AXES CAN BE ADDED IN A SINGLE DIAGNOSTIC <<<<
```

2 Examples

Variation of the density of species `electron1` from $x = 0$ to 1, every 5 time-steps, without time-averaging.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
end
```

Density map from $x = 0$ to 1, $y = 0$ to 1.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
  axis = y      0      1      30
end
```

Velocity distribution from $v_x = -0.1$ to 0.1.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = vx     -0.1    0.1    100
end
```

Phase space from $x = 0$ to 1 and from $px = -1$ to 1.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
  axis = px     -1      1     100
end
```

Energy distribution from 0.01 to 1 MeV in logarithmic scale. Note that the input units are $m_e c^2 \sim 0.5$ MeV.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = ekin    0.02    2    100  logscale
end
```

x - y density maps for three bands of energy: $[0, 1]$, $[1, 2]$, $[2, \infty]$. Note the use of `edge_inclusive` to reach energies up to ∞ .

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = x      0      1      30
  axis = y      0      1      30
  axis = ekin    0      6      3  edge_inclusive
end
```

Charge distribution from $Z^* = 0$ to 10.

```
diagnostic particles
  output = density
  every = 5
  time_average = 1
  species = electron1
  axis = charge  -0.5    10.5    11
end
```

3 How to view and post-process a particle diagnostic

Each diagnostic produces one file like *ParticleDiagnostic0.h5*, *ParticleDiagnostic1.h5*, etc. They are numbered the same way as the order of appearance in the input file.

A python script *ParticleDiagnostic.py* is provided to view or extract data from these files. To run this script, you will need *python2.7* with the following packages: numpy, matplotlib, pylab, h5py.

First, run python and include the script:

```
python -i scripts/ParticleDiagnostic.py
```

Alternately, you can include this file into your own script using, for example

```
execfile("scripts/ParticleDiagnostic.py")
```

3.1 To prepare the data

```
ParticleDiagnostic(results_path, diagNumber=None, timesteps=None, slice=None,  
                  units="code", data_log=False)
```

- `results_path = _string_`
Path to the directory where the outputs are stored.
(Also, this has to contain one and only one input file *.in)
- `diagNumber = _int_` (optional)
Number of the diagnostic. The first diagnostic has number 0.
If not given, then a list of available diagnostics is printed.
- `timesteps = _int_` (optional)
`timesteps = [_int_, _int_]` (optional)
If omitted, all timesteps are used.
If one number given, the nearest timestep available is used.
If two numbers given, all the timesteps in between are used.
- `slice = { axis : "all", ... }` (optional)
`slice = { axis : _double_, ... }` (optional)
`slice = { axis : [_double_, _double_], ... }` (optional)
This parameter is used to reduce the number of dimensions of the array.
`axis` must be "x", "y", "z", "px", "py", "pz", "p", "gamma", "ekin", "vx", "vy", "vz", "v" or "charge".
Any axis of the same name will be removed with the following technique:
 - If the value is "all", then a sum is performed over all the axis.
 - If the value is _double_, then only the bin closest to the value is kept.
 - If the value is [_double_, _double_] , then a sum is performed between the two values.Example: `{"x": [4,5]}` will sum all the data for x in the range [4,5].
- `units = "nice"` (optional)
If "nice" is chosen, then units are converted into usual units.
Distances in microns, density in cm^{-3} , energy in MeV.
- `data_log = True` or `(False)` (optional)
If True, then log 10 is applied to the output array.

3.2 To obtain the data as an array:

```
ParticleDiagnostic( ... ).getData()
```

This method returns only the data array.

```
ParticleDiagnostic( ... ).get()
```

This method returns the results as a python dictionary. The dictionary is of the form

`{"data":data_array, axis1:axis1_array, axis2:axis2_array, ...}` where:

- *data_array* is the final array containing the data.
- *axis1* and *axis2* are the names of the axes (for example "x" or "px").
- *axis1_array* and *axis2_array* are the locations of the axes bins.

Example:

```
>>> result = ParticleDiagnostic("path/to/my/results", diagNumber=3,  
    slice={"ekin":[1,10]}, timesteps=1000).get()
```

This will take the diagnostic #3 for the timestep nearest to 1000, and sum for all energies between 1 and 10. The results are stored in the variable `result`.

The data can be accessed with `result["data"]`.

If one of the axes is *x*, you can access the locations of the bins with `result["x"]`.

3.3 To plot the data

```
ParticleDiagnostic( ... , figure=1, data_min=None, data_max=None,  
    xmin=None, xmax=None, ymin=None, ymax=None ).plot()
```

- `figure = _int_` (optional)
The figure number that is passed to matplotlib.
If absent, figure 1 is used.
- `data_min = _double_` (optional)
`data_max = _double_` (optional)
If present, output is rescaled before plotting.
- `xmin = _double_` (optional)
`xmax = _double_` (optional)
`ymin = _double_` (optional)
`ymax = _double_` (optional)
If present, axes are rescaled before plotting.

Example:

```
>>> ParticleDiagnostic("path/to/my/results", diagNumber=1, slice={"y":"all"},  
    units="nice").plot(figure=1,data_min=0, data_max=3e14)
```

This will take the diagnostic #1, and sum the grid over all the *y* axis. Then it will plot the resulting array in figure 1 from 0 to 3e14.

3.4 To simultaneously plot multiple diagnostics in the same figure

```
multiPlot(diag1, diag2, ... , figure=1, shape=None)
```

- `diag1` = diagnostic prepared by `ParticleDiagnostic(...)`
`diag2` = diagnostic prepared by `ParticleDiagnostic(...)`
...
- `figure` = `_int_` (optional)
The figure number that is passed to matplotlib.
If absent, figure 1 is used.
- `shape` = `[_int_ , _int_]` (optional)
The arrangement of plots inside the figure. For instance, `[2, 1]` makes two plots stacked vertically, and `[1, 2]` makes two plots stacked horizontally.
If absent, stacks plots vertically.

Example:

```
>>> A = ParticleDiagnostic("path/to/my/results", diagNumber=0)
>>> B = ParticleDiagnostic("path/to/my/results", diagNumber=1)
>>> multiPlot( A, B, figure=1 )
```

This will plot the diagnostics #0 and #1 on the same figure, and make an animation for all available timesteps.

3.5 Other tips on managing plots

After you have prepared a diagnostic with `ParticleDiagnostic(...)`, you **cannot** change anymore the following arguments: `results_path`, `diagNumber`, `timesteps`, `slice`, `units` and `data_log`.

However, you can change the plotting parameters using the `.plot()` or the `.set()` functions:

```
>>> A = ParticleDiagnostic("path/to/my/results", diagNumber=0, figure=1, data_max=1)
>>> A.plot( figure=2 )
>>> A.set( data_max=2 )
>>> A.plot()
```

Another cool thing is that you can change the colormap for 2D plots, with the `cmap` argument. For example, you can plot with a gray colormap using

```
>>> A.plot( cmap = "gray" )
```

Many colormaps are available from the *matplotlib* package. With `cmap=""`, you will get an error `Colormap is not recognized`, but it lists all the available colormaps.

4 Tutorial

If you don't know how to run SMILEI, please refer to the appropriate documentation first. The commands can vary depending on your system and installation. A typical example of the command to run SMILEI is: `mpiexec -np 1 smilei mycase.in`

4.1 Running the test case

In the `benchmarks` directory, we provide a test case `tst1d_6_particle_diagnostic.in`. This case is very simple: it consists of a one-dimensional uniform neutral plasma composed by ions and electrons. The electrons all have a drift velocity of $0.05c$.

Run this case using SMILEI and collect the results in a directory of your choice. In this tutorial, we suppose that the results are in the directory `tst1d_6_particle_diagnostic`. Make sure this directory contains the input file `tst1d_6_particle_diagnostic.in` and the output files `ParticleDiagnostic0.h5`, `ParticleDiagnostic1.h5`, etc.

An example of the commands you may use from a UNIX *terminal* (or *console*) is

```
$ mkdir tst1d_6_particle_diagnostic
$ cp benchmarks/tst1d_6_particle_diagnostic.in tst1d_6_particle_diagnostic
$ cd tst1d_6_particle_diagnostic
$ mpiexec -np 1 smilei tst1d_6_particle_diagnostic.in
$ cd ..
```

4.2 Starting *python* and listing available diagnostics

From the same terminal, launch *python* using the command

```
$ python -i scripts/ParticleDiagnostic.py
```

You are now in the *python* prompt.

Obtain a list of available particle diagnostics using

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic')
Printing available particle diagnostics:
-----
Diag#0 - density of species # 1
    Every 4 timesteps, averaging over 2 timesteps
    x from 0.0 to 6.28319 in 100 steps
    vx from -0.1 to 0.1 in 100 steps
Diag#1 - density of species # 0
    Every 4 timesteps, no time-averaging
    x from 0.0 to 6.28319 in 100 steps
    vx from -0.001 to 0.001 in 100 steps
Diag#2 - density of species # 1
    Every 10 timesteps, averaging over 5 timesteps
    ekin from 0.0001 to 0.1 in 100 steps [ LOG SCALE ]
```

Look at the diagnostic #0: it is the density of species #1 (here, electrons) with two axes: the position x and the velocity v_x . In other words, it is the phase-space of electrons.

4.3 Plot a diagnostic result at $t = 0$

To plot the phase-space in the initial conditions, use

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic', 0, timesteps=0 ).plot()
```

A window appears (see Figure ??). We can see that the electrons have indeed a drift velocity of $0.05c$.

To obtain the equivalent plot for the ions, use the diagnostic #1 with the command

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic', 1, timesteps=0 ).plot()
```

This results in the plot in Figure ?. The ions have a zero average velocity.




Figure 1: Phase-space of electrons at $t = 0$.




Figure 2: Phase-space of ions at $t = 0$.

4.4 Make animated plots

Use the following command to have an animation of the electron phase-space with time:

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic', 0 ).plot()
```

You will see the electron velocity oscillate from $0.05c$ to $-0.05c$. This is due to the fact that we are simulating a plasma wave with infinite wavelength.

Note that all the available timesteps are animated. If you want to only animate between timesteps 20 and 60, use

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic', 0, timesteps=[20,60] ).plot()
```

4.5 Make multiple plots on the same figure

Use the following commands to have the animation with both electrons and ions on the same figure:

```
>>> A = ParticleDiagnostic('tst1d_6_particle_diagnostic', 0 )
>>> B = ParticleDiagnostic('tst1d_6_particle_diagnostic', 1 )
>>> multiPlot(A, B)
```

4.6 Plot sections (“slices”) of the array

The diagnostic #0 that we plotted in Figure ?? is the electron phase-space. Let us say we want to sum over the data that is contained between $x = 3$ and 4, and plot the result as a function of v_x . This is achieved by the argument `slice`:

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic', 0, timesteps=0,  
    slice={"x":[3,4]} ).plot()
```

The result is shown in Figure ?. We can see that the peak is located at $v_x = 0.05c$, as we have already found before.




Figure 3: v_x distribution of electrons contained between $x = 3$ and 4, at $t = 0$.




Figure 4: x distribution of electrons contained between $v_x = -0.1$ and 0.1 , at $t = 0$.

Now, let us do the slice on v_x instead of x .

```
>>> ParticleDiagnostic('tst1d_6_particle_diagnostic', 0, timesteps=0,  
    slice={"vx":"all"} ).plot(data_min=0, data_max=11)
```

By choosing `"all"` in the argument `slice`, all the velocities v_x are sliced. In our case, as our diagnostic goes from $v_x = -0.1$ to 0.1 , these limits are used.

Note that parameters `data_min` and `data_max` are used to have a nicer plot.

The result is shown in Figure ?. We obtain a constant density of $10n_c$, which is what was chosen in the input file.